Name	Bytes	Datatype	Description
TimeStamp	8	double	numeric value of time and date recording
			started
SampRate	8	double	sampling rate in Hz, true sampling <b>interval</b> is approximately round(1e6/SampRate) in microseconds
ChannelNumber	1	uint8	number of channels in the file, for the Arduino, this is typically 1
charLength	1	uint8	number of characters in the Channel name
ChannelName	charLength	char	character array of the channel name
data	inf*	uint16	16-bit values for the analog data of the sensor.
			This extends to the end of the file. To convert
			to voltage, multiply by 5/1023

These two rows below are called in a loop until the number of channels has been reached